

Getting External Mail

You can use Webmail Direct to access other POP mail servers.

To add an external POP mail server:

1. Click **External Mail**.

Result: The **External Mail** page displays. If there are no configured external POP servers, a message displays indicating that you must create one. If you have already added POP servers, profile data on each configured external mail account displays.

2. Click **Add POP Server**.

Result: The **Add/Edit POP Server** page displays.

3. Enter the following data.

- Mail server data:
 - **Description:** A name for the account, for example "Personal".
 - **POP Server Name:** The name of the POP server for the account that you are adding.
 - **User Name:** Your user name for the account that you are adding.
 - **User Password:** Your user password for the account that you are adding.
 - **Confirm Password:** Reenter your password for confirmation.
 - **Port Number** (default 110): The default port for POP connections.
- Select or deselect the message handling options:
 - **Leave messages on POP server** (selected by default): If you want your messages to remain existing on the POP server, still accessible to you on other accounts, leave this option selected. If you deselect this option, all messages are deleted from the POP server when they are downloaded.
 - **Get new messages only** (selected by default): This option causes the POP server to download only messages that have not been previously downloaded to your Webmail account.

取得外部郵件

您可使用 Webmail Direct 來存取其他 POP 郵件伺服器。

如要新增外部 POP 郵件伺服器:

1. 按一下 [外部郵件]。

結果: 顯示 [外部郵件] 網頁。如果未配置外部 POP 伺服器, 則會顯示訊息, 提示您必須建立一個外部 POP 伺服器。如果您已新增 POP 伺服器, 則會顯示每個已配置的外部郵件帳號的詳細資料。

2. 按一下 [新增 POP 伺服器]。



結果: 顯示 [新增/編輯 POP 伺服器] 網頁。

3. 輸入下列資料。

- 郵件伺服器資料:
 - **說明:** 帳號名稱, 例如 "Personal"。
 - **POP 伺服器名稱:** 您要新增的帳號之 POP 伺服器名稱。
 - **使用者名稱:** 您要新增至該帳號的使用者名稱。
 - **使用者密碼:** 您要新增至該帳號的密碼。
 - **確認密碼:** 重新輸入密碼以進行確認。
 - **連接埠號** (預設值 110): POP 連線的預設連接埠。
- 選取或取消選取郵件的處理選項:
 - **將郵件留在 POP 伺服器** (預設為選取): 如果您要將郵件留在既有的 POP 伺服器, 您仍可從其他帳戶進行存取, 則將此選項保留選取。如果您要取消選取此選項, 所有的郵件在下載後就會從該 POP 伺服器上刪除。
 - **僅取得新郵件** (預設為選取): 此選項會讓 POP 伺服器僅下載之前未下載至您 Webmail 帳號的郵件。

- Choose message downloading options:
 - **Inbox using filters** (default): All downloaded external mail messages display in your Inbox and are subject to the filters you have configured.
 - **<folder> without using filters** (use the pull-down list to select a folder): All downloaded external mail messages display in the selected folder and are not subjected to any configured filters.
 - **Mail color** (green is default color): The downloaded messages display in the rows of the selected color. You can configure up to ten (10) external mail accounts and assign each a different color. You can also use the same color for all external mail accounts.

Click **Done**.



Result: You are returned to the **External Mail** page and the additional POP mail account profile displays. Click the **Edit** icon  to redisplay the **Add/Edit POP Server** page for that account and make changes. Click the **Delete** icon  to display a delete confirmation page where you can confirm or cancel the delete operation.

To retrieve your external POP account messages:

1. On the **External Mail** page with configured POP accounts, click **Check External Mail**.
Result: The system requests mail delivery from each of your configured POP accounts and displays a status line for each.
2. Click the **Download Folder** link for the POP account whose delivered message you want to read.
Result: The folder where your messages for the selected POP account were delivered opens. The external messages display in rows with the background color you configured.

- 選擇郵件下載選項：
 - **收件夾使用篩選器** (預設)：所有已下載的外部郵件會顯示在您的收件夾中，並受您配置的篩選器所影響。
 - **不使用篩選器的 <資料夾>** (使用下拉式清單來選取郵件夾)：所有下載的外部郵件會顯示在選取郵件夾並不受任何配置的篩選器所影響。
 - **郵件顏色** (預設為綠色)：下載郵件會依選取的顏色顯示。您可配置最多十個外部郵件帳號並個別指定不同的顏色。您同時也可以對所有外部郵件帳號使用相同的顏色。

按一下 [完成]。

結果：您可回到 [外部郵件] 網頁，其中會顯示其他的 POP 郵件帳號資料。按一下 **編輯** 圖示  以重新顯示該帳號的 [新增/編輯 POP 伺服器] 網頁，並可進行修改。按一下 **刪除** 圖示  以顯示刪除確認網頁，您可確認或取消刪除操作。

如要擷取您的外部 POP 帳號郵件。

1. 在配置 POP 帳號的 [外部郵件] 網頁上，按一下配置好的 POP 帳號，按一下 [檢查外部郵件]。
結果：系統會要求從您配置的每個 POP 帳號傳送郵件，並顯示每一個帳號的狀態行。
2. 按一下您要讀取郵件的 POP 帳號 [下載郵件夾] 連結。
結果：開啟選取的 POP 帳號郵件所傳送至的郵件夾。外部郵件以數行顯示，其背景色彩依您的配置顯示。